

cream-test-notified-lease-expired

NAME

cream-test-notified-lease-expired - submit a sequence of jobs and let the lease expires for each job

SYNOPSIS

cream-test-notified-lease-expired [OPTION] -R | --resourceURI RESOURCEURI

DESCRIPTION

Submit a given number of jobs keeping track of their status via CEMonitor notifications. For each job either a lease is registered or a pre-registered lease is used; the lease is not renewed so the job must be cancelled by the service. The status of the job is notified by the CEMonitor. The test keeps a given number of job running on the CE.

OPTIONS

- **-p --consumerPort NUMBER** define the port for the consumer service (DEFAULT is 9000)
- **-D --delegationType STRING** specify the delegation management type: single, one delegated proxy for all submissions, or multiple, one delegated proxy per job (DEFAULT is single)
- **-h --help** Print the man pages for this command
- **--interactive** Enable the test control via terminal (EXPERIMENTAL)
- **-W --leaseTime NUMBER** define the lease time in seconds for a lease, if it is not used a pre-registered lease id (DEFAULT 1200s)
- **-l --logConf STRING** Set the location of the configuration file for log4py, (DEFAULT as provided by log4py)
- **-C --maxConcurrentSubmit NUMBER** define the number of concurrent submit, (DEFAULT is 1)
- **-m --maxRunningJobs NUMBER** set the max number of job which can be enqueued in the service (DEFAULT 100)
- **--nopurge** Disable the purge operation for all jobs submitted (CRITICAL)
- **-n --numberOfJob NUMBER** set the number of jobs to submit (DEFAULT 1)
- **-r --rate NUMBER** set the notification rate in seconds for the subscription on CEMonitor (DEFAULT is 30s)
- **-R --resourceURI STRING** define the URI of the resource under testing, the format is [:/]cream--. This option is mandatory and no default value is defined
- **--sockettimeout NUMBER** Socket timeout in seconds (DEFAULT 30s)
- **--valid STRING** set the voms-proxy duration in the format HH:MM (DEFAULT 00:10)
- **--vo STRING** set the VO name to be used for the test; this parameter is mandatory whenever X509_USER_CERT and X509_USER_KEY are defined, no default is available

ENVIRONMENT

- **GLITE_LOCATION** location of gLite packages (DEFAULT=/opt/glite)
 - **X509_USER_PROXY** location of the user proxy
 - **X509_USER_CERT** location of the user certificate, this variable has priority upon the X509_USER_PROXY variable
 - **X509_USER_KEY** location of the user private key. The key must be protected by a passphrase.
 - **X509_CONSUMER_CERT** location of the consumer certificate, if this variable is set together with X509_CONSUMER_KEY the test suite enables the notifications over secure channel
 - **X509_CONSUMER_KEY** location of the consumer private key, if this variable is set together with X509_CONSUMER_CERT the test suite enables the notifications over secure channel. The key must be protected by a passphrase.
 - **NOTIFIED_LEASE_EXP_CONFIG_FILE** location of the configuration file for this test. The configuration file contains a list of properties (the format is key=value); the set of keys correspond to the set of the long options of this test
-

This topic: EgeeJra1It > CreamTestNotifiedLeaseExpired

Topic revision: r3 - 2009-05-26 - PaoloAndretto



Copyright © 2008-2023 by the contributing authors. All material on this collaboration platform is the property of the contributing authors.

Ideas, requests, problems regarding TWiki? Send feedback