

# Table of Contents

<b>glite-ce-disable-submission</b> .....	<b>1</b>
NAME.....	1
SYNOPSIS.....	1
DESCRIPTION.....	1
OPTIONS.....	1
EXIT STATUS.....	2
EXAMPLES.....	2
SEE ALSO.....	2
Index.....	2

# glite-ce-disable-submission

Section: User Commands (1)

Index

---

## NAME

glite-ce-disable-submission - Disables job submissions to the specified CREAM CE.

## SYNOPSIS

**glite-ce-disable-submission** [**options**] <host>[:<port>]

## DESCRIPTION

glite-ce-disable-submission is an operation supposed to be used only by a "super-user" of the considered CE. It is used to disable job submissions to the considered CREAM CE. So after having issued this command it is not possible to submit anymore new jobs on the considered CREAM CE, while the other operations (job status, job cancellation, etc.) are still allowed.

## OPTIONS

**--help, -h**

Displays command usage.

**--conf file\_name, -c file\_name**

Specifies the user specific configuration file.

**--donot-verify-ac-sign, -A**

Allows the execution of the command even if the VO voms server certificate is not installed.

**--nomsg, -n**

This option makes the command print on the standard output only the result of the operation (or error messages in case of failure). Therefore any warning or info message is suppressed if this option is used.

**--debug, -d**

When this option is specified, debugging information is displayed on the standard output and written also into the file glite-ce-disable-submission\_CREAM\_<username>\_<date>\_<time>.log file under (by default) the /tmp/glite\_cream\_cli\_logs directory.

**--logfile file\_name, -l file\_name**

When this option is specified, a command log file (whose pathname is file\_name) is created.

**--version, -v**

Displays the version of the CREAM CLI software.

## EXIT STATUS

glite-ce-disable-submission exits with a status value of 0 (zero) upon success, and >0 (greater than zero) upon failure.

## EXAMPLES

```
> glite-ce-disable-submission grid006.pd.infn.it:8443
```

Operations for disabling new submissions succeeded

---

The following example shows what happens if the considered user is not a ``super-user" of the specified CREAM CE:

```
> glite-ce-disable-submission grid005.pd.infn.it:8443
```

```
2006-03-09 09:25:20,859 ERROR - MethodName=[disableAcceptJobSubmissions] ErrorCode=[0]
Description=[Operations reserved only to administrator!] FaultCause=[Operations reserved only to
administrator!] Timestamp=[Thu Mar 9 09:25:20 2006]
```

## SEE ALSO

glite-ce-enable-submission, glite-ce-allowed-submission

---

## Index

NAME  
SYNOPSIS  
DESCRIPTION  
OPTIONS  
EXIT STATUS  
EXAMPLES  
SEE ALSO

---

This document was created by man2html, using the manual pages.

Time: 11:20:03 GMT, May 05, 2011

-- MassimoSgaravatto - 2011-05-05

---

This topic: CREAM > GliteCeDisableSubmissionMan

Topic revision: r2 - 2011-10-24 - TWikiAdminUser



Copyright © 2008-2020 by the contributing authors. All material on this collaboration platform is the property of the contributing authors.

Ideas, requests, problems regarding TWiki? Send feedback