

Table of Contents

glite-ce-service-info.....	1
NAME.....	1
SYNOPSIS.....	1
DESCRIPTION.....	1
OPTIONS.....	1
EXIT STATUS.....	1
EXAMPLES.....	2
Index.....	2

glite-ce-service-info

Section: User Commands (1)

Index

NAME

glite-ce-service-info - Returns information about the CREAM service (version, status, etc.)

SYNOPSIS

glite-ce-service-info [options] <host>[:<port>]

DESCRIPTION

glite-ce-service-info is the command used to get information about the CREAM service. Information provided by the command includes the interface version, the service version, the status of the CREAM service.

OPTIONS

--help, -h

Displays command usage.

--conf file_name, -c file_name

Specifies the user specific configuration file.

--level verb_level, -L verb_level

Sets the detail level of information. Possible values for verb_level are 1 and 2.

--donot-verify-ac-sign, -A

Allows the execution of the command even if the VO voms server certificate is not installed.

--debug, -d

When this option is specified, debugging information is displayed on the standard output and written also into the file glite-ce-service-info_CREAM_<username>_<date>_<time>.log file under (by default) the /tmp/glite_cream_cli_logs directory.

--logfile file_name, -l file_name

When this option is specified, a command log file (whose pathname is file_name) is created.

--version, -v

Displays the version of the CREAM CLI software.

EXIT STATUS

glite-ce-service-info exits with a status value of 0 (zero) upon success, and >0 (greater than zero) upon failure.

EXAMPLES

> glite-ce-service-info cream-13.pd.infn.it:8443

Interface Version = [2.1]

Service Version = [1.12]

Description = [CREAM 2]

Started at = [Tue Nov 10 14:42:12 2009]

Submission enabled = [YES]

Status = [RUNNING]

Service Property = [SUBMISSION_THRESHOLD_MESSAGE]->[Threshold for Load Average(1 min): 10
=> Detected value for Load Average(1 min): 0.03

Threshold for Load Average(5 min): 10 => Detected value for Load Average(5 min): 0.03

Threshold for Load Average(15 min): 10 => Detected value for Load Average(15 min): 0.00

Threshold for Memory Usage: 95 => Detected value for Memory Usage: 57.41%

Threshold for Swap Usage: 95 => Detected value for Swap Usage: 2.02%

Threshold for Free FD: 500 => Detected value for Free FD: 204500

Threshold for tomcat FD: 800 => Detected value for Tomcat FD: 107

Threshold for FTP Connection: 30 => Detected value for FTP Connection: 1

Threshold for Number of active jobs: -1 => Detected value for Number of active jobs: 0

Threshold for Number of pending jobs: 40 => Detected value for Number of pending jobs: 0

Threshold for Number of pending commands: -1 => Detected value for Number of pending commands: 0

Index

NAME
SYNOPSIS
DESCRIPTION
OPTIONS
EXIT STATUS
EXAMPLES

This document was created by man2html, using the manual pages.

Time: 11:23:00 GMT, May 05, 2011

-- MassimoSgaravatto - 2011-05-05

This topic: CREAM > GliteCeServiceInfoMan

Topic revision: r1 - 2011-05-05 - MassimoSgaravatto



Copyright © 2008-2022 by the contributing authors. All material on this collaboration platform is the property of the contributing authors.

Ideas, requests, problems regarding TWiki? Send feedback