

MAKETEXT -- creates text using TWiki's I18N infrastructure

- Syntax: `%MAKETEXT{"string" args="..."}%`
- Supported parameters:

Parameter	Description	Default
"text" or string="text"	The text to be displayed.	<i>none</i>
args="param1, param2"	a comma-separated list of arguments to be interpolated in the string, replacing the <code>[_N]</code> placeholders in it.	<i>none</i>

- Examples:

- ◆ `%MAKETEXT{string="Notes:"}%`
expands to

Notes:

- ◆ `%MAKETEXT{"If you have any questions, please contact [_1]."
args="%WIKIWEBMASTER%" }%`
expands to

If you have any questions, please contact grid-operations@lists.cnaif.infn.it.

- ◆ `%MAKETEXT{"Did you want to [[[[_1]]][reset [_2]]'s password]]?"
args="%SYSTEMWEB%.ResetPassword,%WIKIUSERNAME%" }%`
expands to

Did you want to reset Main.TWikiGuest's password?

- Notes:

- ◆ TWiki will translate the `string` to the current user's language *only* if it has such string in its translation table for that language.
- ◆ Ampersands (&) followed by one letter (one of a...z, A...Z -- say, X) in the translatable string will be translated to `X`. This is used to implement access keys. If you want to write an actual amperstand that stays just before a letter, write two consecutive amperstands (&&): they will be transformed in just one.
- ◆ Translatable string starting with underscores (_) are reserved. You **must not** use translatable phrases starting with an underscore.
- ◆ Make sure that the translatable string is *constant*. Specially, do **not** include `%VARIABLES%` inside the translatable strings (since they will get expanded **before** the `%MAKETEXT{...}%` itself is handled).

This topic: TWiki > VarMAKETEXT

Topic revision: r4 - 2010-06-16 - TWikiContributor



Copyright © 1999-2021 by the contributing authors. All material on this collaboration platform is the property of the contributing authors.

Ideas, requests, problems regarding TWiki? Send feedback

Note: Please contribute updates to this topic on TWiki.org at TWiki:TWiki.VarMAKETEXT.